

Chapter 1 Get Started

- 1. Create a new Map Control application project:
 - Open Visual Studio, click File -> New -> Project.
 - Choose templates: Visual C# -> ArcGIS -> Extending ArcObjects.
 - Choose project type: MapControl Application.
 - Input the project name and location path, and the click OK.




2. Add Layout Control:

 Click MapControl (default name: axMapControl1), in the Properities panel, set Dock to "None", then zoom out MapControl




• Choose TabControl from Toolbox, and drag into the application window.



- Drag MapControl into tabPage1 of TabControl, and set Dock property to "Fill"
- Drag PageLayoutControl into tabPage2 of TabControl, and set Dock property to "Fill"



• Edit property "TabPage" of TabControl, as the following graph:



• Set Alignment of TabControl to "Bottem", Dock of TabControl to "Fill".

Now A simple MapControl Application has been built.

Next chapter I will introduce how to sychronize PageLayoutControl and MapControl.